



SnowGem

Wallet Software Snowgem

Installare il GUI Wallet Windows

[Download link for Wallet](#)

Se non presente nel sistema [Download link .Net 4.5](#)

Se non presente nel sistema [Download link java](#)

Per evitare di creare manualmente le cartelle, fare partire il file SimpleWallet vi verrà richiesto di chiudere e riaprire, attendere qualche secondo che il wallet crei i file necessari e chiudere.

Images	04/01/2018 10:16	Cartella di file	
Newtonsoft.Json.dll	03/01/2018 09:13	Estensione dell'ap...	639 KB
SimpleWallet	10/01/2018 20:39	Applicazione	630 KB
snowgem-cli	10/01/2018 10:58	Applicazione	5.663 KB
snowgemd	10/01/2018 10:58	Applicazione	23.175 KB
SnowgemSwingWalletUI	22/12/2017 14:18	Executable Jar File	207 KB
snowgem-tx	10/01/2018 10:58	Applicazione	14.039 KB

Aprire il wallet gui con il file SnowgemSwingWalletUI

Swing Wallet UI for Snowgem® - 0.73 (beta)

Main Wallet

Overview Own addresses Send cash Address book

Sn wgem

Transparent balance: 0,00 SNG
Private balance: 0,00 SNG
Total balance: 0,00 SNG

Transactions:

Type	Direction	Confirmed?	Amount	Date	Destination Address
------	-----------	------------	--------	------	---------------------

snowgemd status: **RUNNING**, Resident: 229.708 MB
Wallet: C:\Users\WorkMiner\AppData\Roaming\Snowgem\wallet.dat (not encrypted)
Installation: C:\Users\WorkMiner\Desktop\snowgem-1.0.5-windows64, Blockchain: C:\Users\WorkMiner\AppData\Roaming\Snowgem
System: Windows 7

Blockchain synchronized: **100%** ☆
Up to: 2-feb-2018 23.32.49
Network: **4 connections** ⇄

Configurazione mining:

Username: wallet.nome - Password: x

Server: minepool.ch

Porta:3052

Scarica il miner appropriato e configuralo



NVIDIA.

Download Claymores miner [Qui](#)

Download EWBF miner [Qui](#),

Download DSTM miner [Qui](#),

Claymores:

Comandi per avviare il miner:

```
ZecMiner64.exe -zpool <server>:<port> -zwal <address>.<worker> -zpsw x -allpools 1 <threads>
```

Example:

```
ZecMiner64.exe -zpool minepool.ch:3052 -zwal s1VhQFdXT4xsZAoTrxaax51qFyYqyahYFZ1.guidach -zpsw x -allpools 1
```

EBWF miner:

Comandi per avviare il miner:

```
miner.exe --server <server> --user <address>.<worker> --pass x --port <port>
```

Example:

```
miner.exe --server minepool.ch --user s1VhQFdXT4xsZAoTrxaax51qFyYqyahYFZ1.guidach --pass x --port 3052
```

DSTM miner:

Comandi per avviare il miner:

```
zm.exe --server <server> --user <address>.<worker> --pass x --port <port>
```

Example:

```
zm.exe --server minepool.ch --user s1VhQFdXT4xsZAoTrxaax51qFyYqyahYFZ1.guidach --pass x  
--port 3052
```



Download Claymores miner [Qui](#)

Claymores:

Comandi per avviare il miner:

```
ZecMiner64.exe -zpool <server>:<port> -zwal <address>.<worker> -zpsw x -allpools 1 <thr  
eads>
```

Example:

```
ZecMiner64.exe -zpool minepool.ch:3052 -zwal s1VhQFdXT4xsZAoTrxaax51qFyYqyahYFZ1.guidac  
h -zpsw x -allpools 1
```